

## Siemens PLM Software 技術技巧及新聞

歡迎流覽《Siemens PLM Software 技術技巧及新聞》，希望它能成為 Siemens PLM Software 技術支援團隊將 Siemens PLM Software 最新產品更新、技術技巧及新聞傳遞給用戶的一種途徑

Date: 2020/06/12

### Teamcenter Tips

#### 1. ID 創建規則中無法增加客制化的屬性

軟體版本：

TC11.\*

問題：

在定義新的 ID 創建規則時，客制化的 ID 創建器無法為串聯規則增加屬性




只能看到開箱即用的屬性

Property Name	Data Type	COTS
awb0SupportsStructure	Boolean	✓
awp0CellProperties	String[]	✓
awp0ThumbnailImageTicket	String	✓
object_string	String	✓


解決辦法：

新建 ID 創建規則時，ID 創建器欄位預設值為 Fnd0BaselIdGenerator。

此處需要設置為使用者客制化的 ID 創建器物件



此後，當需要增加串聯規則時，只需要按下增加按鈕，就可以增加定制化的屬性。



## 2. 執行 audit\_purge 工具時間格式錯誤.

問題:

執行 `audit_purge` 工具時，遇到時間格式的錯誤:

```
>audit_purge -u=infodba -p=***** -g=dba -logtype=Fnd0GeneralAudit -archive -
archivelocation=D:\temp\wf_archive -created_before=13-04-15,18:00
```

錯誤資訊如下:

```
ERROR - 2019/11/22-17:03:37.283 UTC - NoID - 38053: Specified value 04 is not a
valid month. - DATE_convert_format_date_to_date_t received error from
DATE_string_to_date on '13-04-15,18:00' format '%d-%b-%Y %H:%M' -
Teamcenter.CoreModelGeneral.fclasses at
d:\workdir\tc121w1213_64\src\core\fclasses\iman_date_itk.cxx(1009)
```

```
ERROR - 2019/11/22-17:03:37.284 UTC - NoID - 515032: The given date is invalid.
```

軟體配置:

```
Product: TEAMCENTER
Application: AUDIT_MANAGER
Version: V12.1
```

方法:

正確的時間格式為：dd-Mon-yyyy hh:mm

例如：

```
>audit_purge -u=infodba -p=***** -g=dba -logtype=Fnd0GeneralAudit -archive -
archivelocation=D:/temp/wf_archive -created_before=13-APR-15,18:00
```



## Tecnomatix Tips

### 3. 是否有命令列的方式刪除 inactive sessions?

問題/症狀：

是否有命令列的方式, 刪除在 admin console 中找到的 inactive sessions?

**Hardware/Software Configuration :**

Platform: INTL64

OS: WINDOW

OS Version: 2012\_R2

Product: TECNOMATIX

Application: EM-SERVER

Version: V\_UNKNOWN

Function: ADMIN\_TOOLS

解決方法：

有的. 有個命令叫做 "eMServerAdmin.exe". 下面是運行這個命令的一個簡單例子：

```
eMServerAdmin -user administrator -killsessions
```

這樣就能殺死 inactive 的 'eMServer sessions' 。

要殺死 active 的 sessions, 您仍然要在 AdminConsole UI 中做。

Greater China

ME&S Service Team

PRC Helpdesk (Mandarin): 800-810-1970/021-22086635

Taiwan Helpdesk (Mandarin): 00801-86-1970

HK Helpdesk (Cantonese): 852-2230-3322

Global Technical Access Center: <http://www.siemens.com/gtac>

Siemens PLM Software Web Site: <http://www.plm.automation.siemens.com>

Siemens PLM Software (China) Web Site: [http://www.plm.automation.siemens.com/zh\\_cn/](http://www.plm.automation.siemens.com/zh_cn/)

~~~~~  
此e-mail newsletter 僅提供給享有產品支援與維護的Siemens PLM 軟體使用者。當您發現問題或希望棄訂，請發送郵件至 [helpdesk\\_cn.plm@siemens.com](mailto:helpdesk_cn.plm@siemens.com) 聯繫，如棄訂，請在標題列中注明“棄訂”

~~~~~